Blue Cat's Axiom User Manual



"The next generation: your axe beyond the limits"





- Introduction
 - <u>Description</u>
 - System Requirements
 - Installation
 - First Launch
- <u>Using Blue Cat's Axiom</u>
 - Introduction
 - <u>The User Interface</u>
 - Operation
- <u>Standalone Application Basics</u>
- Blue Cat Audio Plug- ins Basics
 - User Interface Basics
 - <u>Controls</u>
 - Keyboard
 - Mouse
 - Presets Management
 - MIDI & Automation Control
 - More
- Plug- in Settings
 - The Global Settings Window
 - The Preset Settings Window
- <u>About Skins</u>
 - <u>Changing the Skin</u>
 - <u>Create a Custom Skin</u>
- <u>More</u>
 - Extra Skins
 - Tutorials
 - Updates
 - Versions History

Note: An online version of this user manual is available here.

Description

Blue Cat's Axiom is a powerful and open multi effects processor and amp simulation software for guitar and bass. Based on the acclaimed <u>Destructor</u> plug- in for amp simulations, Axiom offers an **infinite number** of exceptional **tones** for your axe.

Axiom includes **two amp simulations channels** (with pre and post effects) that can be mixed together or used alternatively like a real amp. You can choose your amp models from hundreds of presets or launch the **amp editor** to build your own, with complete control over the tone. Additional input and master sections let you adjust the tone at the input and the output of Axiom, with 4 additional effect slots each and an integrated **high precision tuner**. A **brickwall limiter** also protects the output from overshoot.

Axiom includes more than **70 built- in effects** that can be loaded in any of the **32 plug- in slots**, including a built- in version of <u>Late</u> <u>Replies</u> for creative delays and reverbs, and a built- in version of <u>Destructor</u> to add your own distortion pedals, cabinets or additional amp simulations.

Blue Cat's Axiom is not limited to its built- in effects: these slots can also host **third party Audio Unit**, **VST or VST3 plug- ins**: you can use your favorite plug- ins anywhere in the signal chain and expand Axiom's capabilities.

And because playing alone is not so much fun, we have added a **tools section** with 3 additional slots to load virtual instruments: add a metronome, a drum machine, sequencer or your keyboardist's favorite synthesizer there to get it mixed with your guitar.

If you are looking for amp simulation software without the effects, see the <u>Destructor plug- in</u>. For a plug- in host & multi- effects processor without amp simulation, check out Blue Cat's <u>PatchWork</u>.



Typical applications: Unlimited Guitar & bass amp simulation with effects, VST, VST3 and Audio Unit hosting.

Credits: this plug- in includes several factory presets created by Hans Van Even.

System Requirements

Windows

- An SSE2- enabled processor (Pentium 4 or newer).
- Microsoft Windows Vista, Windows 7, 8 or 10.
- For the plug- in, any VST / AAX compatible host software (32 or 64 bit).
- For the standalone application, an ASIO, MME or WASAPI compatible audio interface (ASIO recommended).

For more information about supported platforms, see our <u>FAQ</u>.

Demo Limitations

- 5 instances of the plug- in allowed per session.
- The effect is bypassed for half a second every minute.

Mac OS X

- An Intel or Apple Silicon processor.
- Mac OS 10.9 or newer.
- For the plug- in, any VST / Audio Unit / AAX compatible application (64- bit) .
- For the standalone application, a Core Audio compatible audio interface.

Installation

The standalone version does not require any host application and can be run without requiring any third party application.

The plug- ins versions cannot be run standalone: they require a host application (see the <u>System Requirements</u> chapter for more information). Depending on which host application you use, you might need to install the plug- ins in different locations.

Before installing one of the plug- in versions, you should close all your host applications.

Windows

Install

All versions of the plug- in provide an installation program. Follow the steps of the wizard to install the software on your machine. During the installation you will be asked where you want the software to be installed. For the VST version, you should install the plug- in inside the VST plug- ins folder used by your host application(s). The default path set in the installer should work for most applications, but you should check your host software documentation to know where it looks for VST plug- ins. For other plug- in types, you should just use the standard path.

Some applications will not automatically rescan the new plug- ins, so you might have to force a refresh of the plug- ins list.

Upgrade

When a new version of the software is released, just launch the new installer: it will update the current installation.

Uninstall

To uninstall the software, simply launch the "Uninstall" program that is available in the start menu or in the configuration panel. It will take care of removing all files from your computer.

Мас

Install

On Mac the plug- ins are available as drive images with an installer. After download, double click on the dmg file to open it. You can then double click on the installer (.pkg file) to install the package.

Note for Mac OS 10.15 Catalina or newer: you will have to right click on the installer and select "Open" instead of double clicking on the file to launch the installation.

Upgrade

When a new version of the software is released, just launch the new installer: it will update the current installation.

Uninstall

To uninstall the software, simply remove the component(s) from their install location (move them to the trash):

- Standalone applications are installed in the / Applications folder
- AAX plug- ins are installed in the / Library/ Application Support/ Avid/ Audio/ Plug- Ins/ folder
- Audio Units (AU) are installed in the / Library/ Audio/ Plug- Ins/ Components/ folder
- RTAS Plug- ins are installed in the / Library/ Application Support/ Digidesign/ Plug- Ins/ folder
- VST plug- ins are installed in the / Library/ Audio/ Plug- Ins/ VST folder
- VST3 plug- ins are installed in the / Library/ Audio/ Plug- Ins/ VST3 folder

If you want to completely remove all settings and configuration files, you can also remove these additional directories that may have been created on your computer:

- ~/ Library/ Preferences/ Blue Cat Audio/ [Plug- in name and TYPE], where TYPE is VST, AU, RTAS or AAX: global preferences.
- ~/ Library/ Preferences/ Blue Cat Audio/ [Plug- in name]: license information
- ~/ Documents/ Blue Cat Audio/ [Plug- in name]: user data, such as presets, additional skins and user- created plug- in data.

Please be aware that these directories may contain user data that you have created. Remove these directories only if you do not want to reuse this data later.

First Launch

Standalone Application

Once the application has been installed, simply double click on its icon to launch it. On Mac, the application will be located in the 'Applications' folder if using the default install location. On Windows, you will find it in the start menu.

The first time you launch the application, it will ask you if you want to configure the audio interface:



It is recommended to configure the audio interface before using the application, but you can still do it later by clicking on the "Edit/ Audio Setup" menu. This opens the Audio/ MIDI Preferences window reproduced below:

Audio/MIDI Preference	es								x
General MIDI In MI	DI Out								
Configura	tion:	Stereo	(2 in-2	out)			~		
Driver Ty		ASIO		,			~	•	
Audio De	vice:	ASIO F	Firefac	e USE	3		~ [
Sample F	late:	44100	Hz				~	·	
Buffer Siz	e:	256					samples		
Aud	io Inputs					Au	dio Outputs		
01. None		~	01.	Analo	og 1	(1)		~	
02. None		~	02.	Analo	og 2	2 (1)		~	
Tempo:		120.0			ham				
		4		_		4	bpm		
Time Sigr	nature:	4			1	4	e e e e e e e e e e e e e e e e e e e		
	T	ap Tem	po Set	up					
	A	die Eneir							
		dio Engir			-				
		ted I/O		-		s			
	R	lestart A	udio E	ngine		_			
								Ok	

If the default setup displayed in the panel does not correspond to your needs, you can do the following:

- Choose the appropriate I/ O configuration, if available.
- On Windows, choose the type of audio driver (ASIO is recommended. If you do not have an ASIO driver, we recommend using the <u>ASIO4All</u> driver).
- Choose the driver to use for audio input and audio output, if available (with ASIO, you can only choose a single driver for both).
- Select the sample rate and buffer size. Increasing the size of the buffer uses less CPU but adds latency.
- Select the audio inputs and outputs to use with the software.
- You can also set the tempo and time signature if relevant.
- Click on "Tap Tempo Setup" if you want to tap tempo with a MIDI controller.

Changes are applied to the application in real time and saved when closing the preferences window. You can see the status of the audio engine at the bottom of the window, as well as the estimated i/ o latency (it depends on the sample rate, buffer settings and selected audio interface(s).

If the status of the engine is 'NOT Running', you may need to change the settings: try to increase the buffer size, change the sample rate (it might not be supported by the interface) or select another audio interface.

The MIDI In and MIDI Out panes let you select the MIDI devices to be used as input and ouput. You can either use them all, none, or select from a list:

Audio/M	IDI Prefe	rences			×
General	MIDI In	MIDI Out			
			I input devices:	All Vone All Selection	
					Ok

Once the this has been setup, you can close the window and start using the application.

Standalone Application: Network Server

It is also possible to use the applications as a "slave" of another application that sends audio and MIDI with the <u>Connector</u> plug- in locally or over the network. To do this you should select the "Network Audio" driver type and "Connector Slave" driver.

Click on the button with 3 dots at the right of the driver name to access the connection settings (see the <u>Connector Manual</u> for more details):

Dri	iver Type:	Network Audio
	udio Device:	Connector Slave
Sa	mple Rate:	44100 Hz ~
-	Connector Slave Sett	lings
	Display Name:	Blue Cat's Axiom Server
nput	RECEIVE FROM	
	Scope:	Eocal Host 🗸 🗸
1	Port:	8080
1	Resampling:	Fast \lor
	SEND TO	
	Scope:	Local Host \sim
	Port:	8081
	Ca	ncel Ok

Note: in this mode, the application will not process audio unless some data is sent to it by an instance of the connector plug- in loaded into an active audio application.

Audio Plug- Ins

Blue Cat Audio plug- ins cannot be run standalone, they require a host application (see the <u>System Requirements</u> chapter for more information). Some host applications will require you to scan the plug- ins before they are available in the application.

If the plug- in is not available in the application, please check that it has been installed in the appropriate directory (with no host application running), and that the host application has scanned it.

Introduction

Blue Cat's Axiom is a multi- effects processor for guitar and bass with included amp simulation. It lets you insert third party plug- ins as well as built- in effects in many locations in the signal path.

Signal Path

Axiom is composed of an **input effects** section, followed by **two parallel amp simulation channels** (A/ B), each one including pre and post effect chains together with an amp simulation module. at the output lies the **master channel**, with 4 effect slots, a **stereo spread** control, post gain and a **brickwall limiter**.

I (+0.0	B VOL PAN PAN	
	TOOLS U 1 U 2 Im ≡ Drum Machine Image: Metronome Image: Metronome	

Three additional "tools" slots to host third party **virtual instruments** are available. Their output is mixed to the main signal after the limiter, and before the output gain, as shown above.

Note: despite its position in the Graphical User Interface (GUI), the tuner is not affected by the input effects.

Mono vs Stereo

Blue Cat's Axiom can be used with several audio I/ O configurations, depending on the host application, plug- in format or the audio format of the track it is inserted on: mono, mono to stereo (M2S) or stereo.

When used with regular mono input, it is strongly recommended to use the **mono to stereo** configuration. In this case, the signal remains mono until the post effects of each amp channel. So input effects, pre effects and amp simulations only process a mono signal, which can save a lot of CPU cycles.

The GUI will show a different icon in pre and post effect chains to show if a mono or stereo signal is being processed:



Mono (left) vs stereo (right) effect chain

Amp Simulation

The two amp simulation modules available in channel A and B are based on the Destructor plug- in:



You can load amp presets and use the built- in controls to adjust the tone, or create your own amp simulation by opening the full amp editor or the tone maps browser. All amp presets are compatible and shared with the <u>Destructor</u> plug- in that also comes as a built- in effect.

Using the built- in Destructor, you can actually insert additional amp simulations anywhere in the signal path, or split the preamp and cabinet simulation in different locations (see the tips section later in the manual).

Built- In Effects

Blue Cat's Axiom includes more than **70 top quality built- in effects** that can be used in all plug- in slots (effect pedals of channel strip slots), next to third party VST, VST3 or AU plug- ins. They include: distortion pedals, Bit Crusher, Chorus, Comb Filters, Compressor, Ducker, Multiple delays and echoes, Harmonizer, EQ and IR Loader, Multimode Filter, Flanger, Frequency Shifter, Gain, Gate, Stereo Pan, Phase Shifter, Phaser, Pitch Shifter, Pitch Bender, Reverb, Stereo Strip, Sweep Filter, Tremolo, Wah, Waveshaper...



Axiom is also available as a built- in plug- in, so that you can load it into itself and share the presets... Built- in versions of the <u>Destructor</u> and <u>Late Replies</u> plug- ins are also included. They will share their presets and settings with the full versions if you already own them.

Built- in plug- ins offer the same preset management and control features as the main plug- in (MIDI learn, undo/ redo, parameters range...). For more details about each effect and its controls, please refer to the included documentation ("?" icon in the toolbar of each plug- in).

MIDI Preset Loading

It is possible to load presets using MIDI (with Bank Select and Program Change messages). More details about MIDI and presets loading is available in the presets section.

Multicore Processing

Axiom includes a multicore processing engine that can spread processing on separate processor cores for each amp channel and tools rack elements. It lets you use all your processor cores at the same time and load more effects or instruments at the same time.

Note: effects that are processed in series (one after the other) cannot be parallelized and do not benefit from multicore processing. Only A/B channels and tools rack elements can be processed independently.

The multicore engine can be activated or deactivated for each preset independently. When using very few plug- ins with low CPU usage in parallel, the cost of multicore processing can be higher than the benefits (you can check the CPU usage with the built- in CPU meter at the bottom right of the user interface).

Performance also depends on the host application and its own multicore processing strategy, so you may want to try and compare with or without multicore enabled.

The User Interface

Note: The main toolbar, menus and basic features available with all our plug- ins are detailed in the <u>Blue Cat Audio Plug- ins Basics</u> <u>section</u>.

Overview

The user interface mostly follows the signal flow described in the previous chapter from left to right and top to bottom:



Main Components

- 1. The **main toolbar**, with from left to right: the bypass button, in and out gain controls, the main toolbar buttons, the presets manager and text display LCD.
- 2. The input section, with effect slots, tuner and pre-gain.
- 3. The Amp channels.
- 4. The output section, with effect slots, stereo spread, gain and limiter controls.
- 5. The tools rack, to host third party virtual instruments.
- 6. Real time workload meter that measures CPU load.

Meters

Level meters are available to monitor the audio level at many stages of the processor. Please note that no clipping happens between modules, so it is not a necessity to keep levels below 0 dB. It is however a good practice, as some built- in effects and third party plug- ins may be sensitive to the absolute audio level (dynamics processors, distortions...)

The reverse blue meter next to the output level meters displays the gain reduction performed by the brickwall limiter. Metering can be disabled in the main toolbar.

The main toolbar



- 1. Main plug- in menu (access presets, global settings, ...).
- 2. Show/ Hide controls settings menu (MIDI learn, response curve, lock, effects bypass lock...).
- 3. Undo/ Redo.
- 4. User manual.
- 5. Open the about box.
- 6. Global GUI zoom control.
- 7. Show/ hide level meters.
- 8. Activate multicore support.
- 9. Show/ hide the presets browser.
- 10. Show/ hide controls for pre- fx pedals.
- 11. Show/ hide controls for post- fx pedals.
- 12. Show/ hide the tools rack.
- 13. Show/ hide assigned controls (controls mapped from hosted effects or amp sims).
- 14. Activate tail spillover for Axiom, A/ B channels or pre & post FX.
- 15. GUI settings lock (to prevent GUI layout changes when loading presets).
- 16. Show the preferences pane for plug- ins hosting.

Note: some controls may display additional information in the preset LCD (below the name of the current preset) when hovering the mouse on them, so you may want to keep an eye on this area!

Locks

Several locks are available to **prevent changes while loading presets**: when the lock is active, loading presets will not change the settings of a locked section. A general UI lock is also available in the toolbar, if you want to keep the same user interface settings (GUI layout, opacity, plug- in windows...) while browsing presets.

Π	
	►E
	+24 -

The Input Section

The signal enters the input section right after the main input gain. The lock located at the top of the input column locks the entire input section (including plug- in settings), so that they are not changed while loading global presets.

On the right you have access to a menu that manages the input effects chain: you can load/ save presets or copy the entire chain to paste it in another instance or at another location in Axiom (pre or post fx, master fx...).

The tuner (disabled by default) can be enabled by clicking on it. You may want to disable it once in tune, to save CPU and avoid being distracted while playing.

Note: by saving the current state of the plug- in using the "Save as User Default" function, you can override the default state of the tuner.

At the bottom of the section, the slider adjusts the gain at the output of the section, with a level meter for monitoring.

A and B Channels

At the top of the middle section you will find the main controls for the A and B amp simulation channels:



Each channel can be enabled independently, with its own volume and pan controls. Clicking in the rectangular area around each channel selects the corresponding channel and displays its controls in the area below.

The mix knob lets you blend channels together, or smoothly switch between them. You can also click on the "A" and "B" letters to quickly switch between channels, or on "MIX" to switch between A, B and A +B.


The menu buttons for each channel let you load and save sub- presets that contain the settings of each channel separately. You can also copy/ paste between channels.

Channels Details

Channels A and B are identical and offer the exact same user interface.

Pre and Post FX

Pre effects are applied before the amp simulation, whereas post effects are applied after, but they offer the same capabilities dedicated at chaining effects.



The entire section can be locked to keep its settings unchanged when loading global or channel presets. The power button next to the title can be used to disable the entire chain.

Each pedal slot can host a built- in or third party effect plug- in (more details later in the manual). Despite their different aspect, pedal slots have the exact same behavior and features as the other plug- in slots that can be found in the input and master sections.

At the top right of the section you will find a presets menu to manage sub- presets for the section. The settings can also be copied and pasted from and to other effect chains.

When enabled in the main toolbar, individual controls from hosted plug- ins can be displayed below the chain for direct access. It also works for third party plug- ins that expose their parameters.

Amp Simulation

At the core of Axiom you will find the amp simulator (one per channel):



Using the presets manager at the top of the amp, you can select an amp model from hundreds of presets (shared with the) and then tweak the sounds with the knobs. Their behavior depend on the selected amp preset (they may have different range and the bass, mid and treble controls may affect different frequencies depending on the selected amp preset).

Like other sections, the amp simulator has a lock control and a bypass button.

At the top right of the amp module, you will find in order, from left to right:

- A menu button to access parameters mapping options, MIDI I/ O assignments and presets.
- The gear icon to display the MIDI control settings buttons for the amp simulation module.
- The tone maps button to launch the tones explorer for the amp simulation: browse amp tones and create new amps in 2D with tone maps.
- The amp editor button to launch the amp simulation editor and access the "guts" of the amp simulation.

The amp simulator behaves like a built- in plug- in that is fully integrated into the user interface of Axiom. So in the first menu, you will find the same options as for plug- ins slots (except that you cannot load plug- ins).

When launching the amp editor, Axiom opens the GUI of the <u>Destructor plug- in</u> to give you full control over the simulation:



You can also customize the graphical user interface so that the look and feel of the amp matches the tone you have created: the look and feel selected in the amp editor is reflected in the main Axiom screen.

For more details about the amp editor and how to build your own amp tone, please refer to the <u>Destructor user manual</u> that is also available from the toolbar of the amp editor user interface (question mark icon).

Another option to browse and create new amp tones is to use tone maps: they let you browse existing amp presets in two dimensions and morph between them.



You can find your own tone without having to deal with the amp simulator and its parameters: just follow the presets, and find the right spot on the map.

The Master Section

Like with the input section, the master section has its own lock and effect chain sub- presets controls, accessible next to the title.


Right before the brickwall limiter (that can be disabled with the icon at the top of the level meters), the stereo spread control can reduce the stereo width.

The post gain control lets you adjust the level before the brickwall limiter that protects the output of the plug- in (and your ears...).



The Tools Section

The tools section offers three additional plug- in slots for virtual instruments:



You can load third party instruments (Axiom does not include built- in instruments) such as a drum machine, a metronome, synths, a sequencer... They will be mixed with the guitar signal at the output of the application or the plug- in. They can be controlled via MIDI or play in sync with the tempo if they support it.

The volume of each instrument can be adjusted using the knob next to it, and the section has a lock and presets menu as usual.

Workload Meter

The workload meter on the bottom right of the user interface gives an idea of the amount of cpu used by the plug- in to process audio frames:




It measures the *realtime workload*, which corresponds to the time spent processing an audio buffer compared to its duration. This value may be impacted by other tasks running on the system.

In general the average value gives a good idea of the cpu usage of the plug- in, while the peak value is an indication of potential audio dropouts (if larger than 100% for too long), that may be caused by overall system load (not just the plug- in's audio processing).

The workload meter becomes orange then red when the peak load grows. Hover the mouse on the meter to see numerical values in a tooltip.

Browsing Presets

In order to browse both factory and user presets, you can either use the simple presets menu or open the full featured presets browser from the toolbar that remains visible until you close it:



Click on preset files and folders to open them, or use the arrows to navigate between displayed presets. You can navigate upward in the folders tree by clicking on the current folder at the top. Type in the search box to find presets by name (it also searches in folder names). The search is performed recursively in the currently selected folder (displayed at the top).

Search Tips: you can search for multiple terms by separating them with commas. Wildcards are also supported (with * and ? characters), but they are applied to the full path of the preset. For example, to search for all presets containing the word "phase", type **phase** in the search box. To look for these presets only in the factory presets, you can type *Factory Presets/*phase**.

Both global plug- in presets (main) and sub- presets for each section can be found in the presets browser - just click on the appropriate category to find them. The main tabs let you choose between main presets, channel A or B and "more":



For each channel, you can browse channel presets (containing settings for all subsections), or individual pre or post effect chains presets, or amp models:

Presets X					
الم Main					
	●● Pre FX	اً][Amp	Post FX		

Input, master and tools racks settings can be found in the "more" tab ("..."):

	Presets					
الم Main						
	Input	≜	Tools			

Using Built- in Effects, VST, VST3 or Audio Unit Plug- Ins

Note: before inserting VST plug- ins, it is strongly recommended that you setup your main VST plug- ins directory in the preferences pane, as detailed later in this manual (this setting does not affect VST3 plug- ins).

Warning: in a 64- bit application you can only load 64- bit plug- ins, and in a 32- bit application you can only load 32- bit plug- ins, unless your are using a third party bridging application.

Each plug- in slot lets you insert a plug- in. When clicking on an empty slot, the following menu appears:

	Select	>
	Load VST	
	Load VST3	
	Paste	
	Paste with Map	
~	Track Undo	

The "Select" item lets you load built- in effects, or choose a favorite third party plug- in directly from the menu if you have saved any.


Selecting "Load VST" will open a standard system window where you can select the VST plug- in you want to load. If the preferences have been properly set, the window should open the appropriate location where you can find the VST plug- ins.

Selecting "Load VST3" will open a standard system window where you can select the VST3 plug- in to be loaded.

On Mac, an additional "Load AU" menu item is available to load Audio Units. It opens a file open dialog in the standard location for Audio Units on your system. **Note:** if you want to load the system Audio Units provided by Apple, you will need to open the CoreAudio component located in the / System/ Library directory.

You can also choose to paste an existing VST, VST3 or AU plug- in if previously copied into the system clipboard from another slot. When using the "Paste with Map" command, if the plug- in in the source slot had mapped parameters, these parameters will be added to the map until no more assignable parameters are available.

Once a plug- in has been loaded into a slot, a mouse click will display the following plug- in menu that offers various controls over the plug- in:



- Show (Hide) Editor: display or hide the plug- in's user interface.
- Bypass: toggle bypass for the plug- in.
- Presets: access the plug- in's factory presets if any, and load/ save presets files in the plug- in's native format (fxb/ fxp, vstpreset or aupreset).
- Cut: copy the plug- in and its settings into the system clipboard and remove it from the slot.
- Copy: copy the plug- in and its settings into the system clipboard. Once copied, it can be pasted to any other slot, in any instance of the Axiom plug- in (even in a different application).
- Save As: save the plug- in in the slot and its settings as a favorite. Favorites are saved in the plug- in documents folder and can be organized using folders to appear later in sub menus.
- Center Editor: bring back the editor of the plug- in to the center of the screen, in case you cannot find it.
- Select: select a plug- in and its settings from the favorites list.
- Load VST: load another VST plug- in in the slot (will replace the existing plug- in if any).
- Load VST3: load another VST3 plug- in in the slot (will replace the existing plug- in if any).
- Load AU (Mac only): load another Audio Unit plug- in in the slot (will replace the existing plug- in if any).
- Paste: paste a plug- in and its settings from the system clipboard into the slot.
- Paste with Map: paste a plug- in, its settings and mapped parameters from the system clipboard into the slot. Parameters are remapped in order, until no more assignable parameter is available.
- Params Map: lists the plug- in's parameters that can be mapped for automation, and lets you assign them to external controls (see the next paragraph).
- MIDI In: select the MIDI port(s) this plug- in is receiving data from (see below).
- MIDI Out: select the MIDI port(s) this plug- in is sending MIDI data to (see below).
- Audio I/ O: opens the audio i/ o routing window for this plug- in (see below).
- No Plug- in: remove the plug- in.
- Rename: rename the instance of the plug- in. Setting an empty name reverts back to the plug- in's default name.
- Track Undo: toggle undo tracking for the slot. If enabled, inserted plug- ins changes will be inspected and added to the Axiom plug- in undo history when possible. Please note that some plug- ins may not work properly when this feature is enabled. It is also recommended to disable this feature when controlling a plug- in with MIDI events generators such as Blue Cat's <u>DP Meter Pro</u> or <u>Remote Control</u>.

Once a plug- in has been loaded into a slot, the following buttons are available:




Clicking on the power button on the left will bypass/ unbypass the plug- in in the slot. The button on the right can be used to show/ hide the plug- in's editor.

Missing Plug-Ins

In some cases, it may happen that you are working on a workstation that does not have all plug- ins that were previously loaded into your Axiom session. In this case, the Axiom plug- in will display a "Missing Plug- in" message on corresponding slots. You can still continue working on your session: the Axiom plug- in will retain the state of the missing plug- ins as if they were here. The session can be saved later: the data for missing plug- ins will be saved as well, and the session can be restored later without losing data.

For VST and VST3 plug- ins, if the plug- in is missing because of a path issue (the plug- in is located in another directory, or the 64- bit version has a different name from the 32- bit version...), you can choose to relocate the plug- in:




This lets you find the plug- in on your workstation and re- link to it. The state of the plug- in that was previously saved in the preset or the session will be restored, making sure all data is kept.

Note: the plug- in chosen with the relocate function has to be compatible with the plug- in that was originally loaded in this slot. Relocation will fail otherwise.

Mapping Parameters

The "Params Map" item in the plug- in menu lets you map sub plug- in parameters so that they can be automated or controlled with an external control surface. It also lets you view existing mapping for this plug- in if any:



- Map All Params: assign all parameters of this plug- in to remaining controls (in the same order as exposed by the plug- in). The maximum number of parameters that can be mapped is 40.
- Learn Mode (on/ off): when learn mode is on, touching a control in your plug- in's user interface will automatically add it to the parameters map (if the plug- in supports it). Once you are done with parameters assignment, you may want to disable learn mode to avoid mapping unwanted parameters.
- Reset All Assignments: removes all assigned parameters from the params map, for this plug- in. This frees all controls used by previously assigned parameters (for this plug- in only).
- All parameters available for assignment are then displayed in the menu. Clicking on a parameter toggles mapping on or off. When a parameter is mapped, the name of the external control (as displayed in the host application) appears next to it, inside parentheses.

Parameters Mapping works the following way: 44 parameters are available for mapping in Blue Cat's Axiom. They are named "Control 01" to "Control 44". When a sub plug- in parameter is selected for mapping, the first control available within Blue Cat's Axiom is used. Once mapped, the sub plug- in parameter and this control are linked together, so that any change to either of them is reported to the other.

This enables the sub- plug- in to expose its parameters to the outside of the Axiom plug- in. You can for example use these external controls for automation, MIDI control, control surface assignment etc.

If assigned controls are shown in Blue Cat's Axiom ("Show Assigned Controls" button), new knobs will appear when new parameters are mapped, until the maximum number of 44 controls is reached. You can use these knobs to control the parameters or check their names (the name of the mapped parameter is displayed when the mouse is over the knob).

Internal MIDI Routing

Blue Cat's Axiom lets you build your own MIDI connections between inserted plug- ins and the host application. Each slot can be connected to multiple ports to receive and send MIDI events:

			None All Inputs			
		\checkmark	Host	•		None
			Port A	×	\checkmark	All Channels
			Port B	•		Channel 1
ics	No F	lug-i	Port C	•		Channel 2
	Show Editor		Port D	•		Channel 3
zer	Bypass		Port E	•		Channel 4
	Presets	•	Port F	•		Channel 5
in	Cut		Port G	•		Channel 6
	Сору		Port H	•		Channel 7
	Center Editor		Port I	•		Channel 8
in	Load VST		Port J	•		Channel 9
	Paste		Port K	•		Channel 10
in	Paste with Map		Port L	•		Channel 11
	No Plug-in		Port M	•		Channel 12
			Port N	•		Channel 13
	Params Map	•	Port O	•		Channel 14
	MIDI Input	<u> </u>	Port P	•		Channel 15
	MIDI Output					Channel 16
	Rename			(V 1	
✓	Track Undo					

- Host: this port connects to the host application to send (MIDI Out) and receive (MIDI In) events. By default, all slots have their MIDI input connected to the Host.
- Port A to Port P: these are virtual ports that can be used to connect sub plug- ins together.

For the MIDI input of a plug- in you can additionally choose to filter events by channel so that it receives all events for one or several selected channels only. If you just want the plug- in to receive all events without any filter, choose "All Channels" for the selected port.

Using virtual internal ports is simple: connect the output of a plug- in to a port, and the input of another plug- in to the same port. The two plug- ins will then be able to exchange MIDI data (from sender to receiver). Multiple plug- ins can be connected to the same port (as input or output). MIDI events will be gathered from MIDI Outs and redistributed to to all connected MIDI Ins.

However, there is a limitation in which plug- ins can be connected together:

- it is not possible to create feedback loops.
- only a plug- in that processes audio data before another can send MIDI data to this plug- in. It means that a plug- in can receive MIDI data from plug- ins that are located earlier in the audio processing chain only (see the signal flow above). If the plug- in is located in a parallel chain, it can also receive MIDI data from plug- ins that are located in parallel chains above it.

These limitations ensure causality and perfect synchronization of MIDI data exchanged between plug- ins, without latency.

Note: when connecting a plug- in to control its parameters via MIDI, you may want to disable undo tracking on this plug- in, to avoid that to many undo steps are recorded by Blue Cat's Axiom and reduce CPU usage.

Audio I/ O Routing

Using the "Audio I/ O" command in the plug- in menu, it is possible to manually change which audio channels are processed by each plug- in.

Automatic Selection

By default, Blue Cat's Axiom will automatically detect the number of channels to use for each plug- in depending on its own configuration.

About mono plug- ins: in automatic mode, mono plug- ins will process only the first audio channel, and the wet mono output will be copied to all channels. If you want to only apply the plug- in to one of the incoming audio channels instead, you can use the manual configuration.

Manual Selection

Automatic detection may however not work properly for some plug- ins, and you may want to change which channels the effect applies to (for multi- mono effects for example) That's what the audio I/ O window is for:

My Plug-In Audio I/O			×
Audio Inputs:	Automatic (2)		\sim
Audio Outputs:	Automatic (2)		\sim
🗌 Mute un	used channels Ok	Cancel	
By default, audio i/	o selection is	automatic	

By doldar, addio # o ooloolion to addontatio

When selecting a specific number of inputs and/ or outputs instead of using "automatic", you can choose which channels are connected to each i/ o for this particular plug- in:

My P	lug-In Audio I/O		×		
	Audio Inputs:	2 Inputs	~		
	Audio Outputs:	4 Outputs	\sim		
	Input Channels	Output Channel	5		
01.	Channel 1 ~	01. Channel 1	\sim		
02.	Channel 2 ~	02. Channel 2	\sim		
		03. Channel 3	\sim		
		04. Channel 4	\sim		
	Mute unused channels				
		Ok Car	ncel		

manual audio i/ o configuration

Notes:

- if the same channel is selected for multiple outputs, only the last selected plug- in output will be audible (plug- in outputs are not summed).
- By default, all channels that are not used as outputs by the plug- in remain unchanged (copied from the same channels before the plug- in). For example, on a stereo configuration, if a mono plug- in is set to process only channel 1 and use channel 1 as output, channel 2 will remain unaffected. Select **"mute unused audio channels"** to mute these unprocessed channels instead.

Auto vs Manual

In automatic mode, Blue Cat's Axiom will automatically choose the best configuration according to its own audio layout. This is very useful if you are saving your plug- in chains to reuse them with different audio i/ o configurations.

In manual mode, the number of inputs and outputs of the selected plug- in is selected and will not change. It means that you may not be able to use this particular configuration later with another number of audio channels.

The Preferences Pane



In the preferences pane, you can set the default VST plug- ins path by clicking on it or on the button labeled "...". This VST plug- ins directory is used for several purposes:

- It is the default directory that is opened when you want to load a VST plug- in.
- It is used as the root path when saving/ loading presets that include VST effects: the path of VST plug- ins is saved relatively to this root path, so that you can reopen your sessions on different machines that may have different VST paths (typically on a Mac and a PC).

If you happen to have your VST plug- ins installed in several paths, we advise you to choose the VST path that contains most of your plug- ins. You can then use the "User VST plug- ins directory" to define an extra location for plug- ins. This extra path will be used by the Axiom plug- in as an alternative root path to load and save the plug- ins.

Please note that these paths are used for VST2 plug- ins only - they do not affect the location of VST3 plug- ins.

If the "Restore plug- ins editors on open" option is checked (default), when the Axiom plug- in is opened, inserted plug- ins user interfaces will be restored at the same position as when the Axiom plug- in was last closed. If the option is unchecked, all plug- ins user interfaces will be kept closed when re- opening the Axiom plug- in, and their position on screen will not be saved.

When the "plug- ins editors always on top" option is checked, the windows of the hosted plug- ins will be kept on top of all other windows. It can be useful when you want to make sure the hosted plug- ins remain visible all the time. Also, if you are using Cubase on Windows, you may want to check this option to fix the erratic behavior of Cubase's own "always on top" option.

Drag and drop support

The user interface supports drag and drop to manipulate plug- ins easily:

- drag and drop plug- ins between slots (copy or move).
- hold the alt key on Mac and Ctrl key on windows to copy (duplicate) a plug- in instead of moving it.
- drop the plug- in before another to insert it in the chain
- drag and drop plug- ins between several instances of Axiom or accross plug- ins (compatible with the latest preview of Late Replies, MB-7 Mixer and PatchWork).
- drag and drop .dll, .vst, .vst3, or .component files directly from the Finder or Explorer onto plug- in slots.
- drag and drop .plgnfo files (previously saved from the software) directly from the Finder or Explorer onto plug- in slots.
- drag the amp simulator, and drop it on any slot, like any other plug- in.
- drop the amp simulator onto channel A or B to copy the amp model to the other channel.
- Drag and drop amp channel (A or B) to copy the full channel to the other channel.

You can also drag and drop impulse response files (wav, aiff or flac) onto the amp simulator: they will be loaded into the post filter module of the amp (you may need to adjust the EQ or the filters if a built- in simulation was already loaded).

Using the Controls

The various elements of the user interface (knobs, sliders, buttons...) are simple and intuitive to operate, but more information about how to interact with them is available in the "Plug- ins Basics" chapter of this manual.

Operation

This section explores several common use cases for Axiom. A complete list of the parameters exposed by the plug- in is available in the <u>next section</u>.

Exploring the Presets

With its modular architecture, Blue Cat's Axiom offers a wide range of possibilities, so you may want to browse the global presets first and progressively dive into each section: adjusting parameters, loading sub presets, etc.

This is especially true for the amp simulation module that also offers many sub- presets for each section, when opened in the amp editor (please refer to the <u>Destructor user manual</u> for more details).

Also, the built- in <u>Late Replies plug- in</u> is delivered with hundreds of presets for creative delays and reverbs to enrich your tone: check them out! You also can use it for classic spring reverb emulations or vintage tape delays or unbelievable harmony effects.

Creating Your Own Tone

If you want to create your own tone from scratch, we recommend starting like this:

- 1. Adjust the input gain so that input signal peaks are close to 0 dB, without exceeding it.
- Choose an amp preset, or create your own with the amp editor or the tones map browser (more details in the <u>Destructor user manual</u>).
- 3. Adjust the drive and equalizer (bass, mid, treble) to your taste.
- Add pre and post effects, starting with reverb first and continuing with more "creative" effects.



Note: reverb settings usually have an impact on the spectral balance of the amp simulation, so you may want to adjust the equalizer of the amp simulation after adding the reverb. You can also set the reverb first before choosing your amp simulation preset.

Tip: mixing two amp tones using channels A and B can produce very interesting effects, but it is quite difficult to predict the result: unless you pan them left and right, the different responses of the amp simulations will deeply interact with each other. So if you know what you are looking for, you will often get the best results more quickly by adjusting a single amp simulation in details using the editor, rather than using both at the same time.

Controlling Axiom with MIDI

Axiom and built- in effects can all be controlled via MIDI (see the MIDI and Automation chapter) in several ways.

Program Change

You can load global presets for Axiom using MIDI Program Change messages, when the feature is activated in the main presets menu. It also works for individual built- in plug- ins - and some third party plug- ins may also support it.

~	Disabled	MIDI Program Change >
	All Channels	Load
	Channel 1	Revert
•	Channel 2	Save
	Channel 3	Save As
	Channel 4	

Next / Previous Program

For controllers that do not support program change and bamk select protocols, starting with version 1.6 you can also navigate thru presets by assigning the next and previous preset commands to MIDI CC messages:



Individual Parameters

Individual parameters inside Axiom (and each built- in plug- in) can be controlled via MIDI CC. Some third party plug- ins may also support this feature.

However, it is recommended to use mapped parameters to control the effects loaded into Axiom instead: with this method, you can change presets for these plug- ins independently from MIDI control settings. There parameters will also be available for automation control when using Axiom as a plug- in in your favorite DAW. And it is easier to see which parameters are actually in use for MIDI control when reloading a session later... It also applies to the amp simulation modules.




Here is the full procedure:

- 1. Map the parameters you want to control via MIDI with the "Params Map" plug- in menu item (more details in the previous chapter).
- 2. Display mapped parameters and MIDI controls using the appropriate toolbar icons.
- 3. For each parameter, click on the green arrow below the knob to perform MIDI learn or manually set the MIDI configuration (including parameter range, response curve etc.).

Typical use cases: control the bypass switch for each pedal with foot- switches (no mapping required - it is an Axiom parameter), the position of the Wah or Pitch Bender with an expression pedal (mapping recommended).

Locking Control Settings

When using a foot controller to load Axiom presets, if you are not using global MIDI settings (shared accross the system), you may want to lock MIDI control settings, so that they are not modified when loading presets:



It may also be convenient to lock the state of all effects bypass buttons (as shown above), so that they are not affected by preset changes, and match the state of your foot controller. This lets you both load presets and activate/ deactivate pedals individually with a controller and keep the software and the on/ off state of each footswitch in sync.

Note: the state of these locks can be saved in the default preset, using the Save As User Default command.

Dual Input

Sometimes you may want to use channel A and B separately, each one processing a different audio input: for example, if your instrument has a stereo output (piezo and magnetic guitar pickups, Chapman stick...), or if you want to play with two instruments at the same time (remember when you plugged two guitars in the same amp back in the days?).

Using plug- ins audio I/ O routing, it is fairly easy to to do this in Axiom: check the "dual input" factory presets. they use a simple gain plug- in in the first pre- slot of each channel. For channel A, it is configured to receive only channel 1 (left), whereas the gain plug- in in channel B processes only the second channel (right). Here you go! You have two separate signal chains, each one processing a different input!

Gain Ch1 Audio I/O		x		Gain Ch2 Audio	o I/O		×
Audio Inputs: Audio Outputs:	2 Inputs Automatic (2)	>		Audio Inputs: Audio Outputs:		2 Inputs Automatic (2)	× ×
01. Chann 02. Chann			ss ′	01. 02. [Channel Channel		
	Ok	Cancel	P.	/ N°		Ok	Cancel

Note: this requires a stereo audio input.

Mono Effects

When using a stereo configuration, with the audio I/ O panel, you can apply different effects to the left and right channels:

Co Co	- 0 OV	B G OL N F B	Delay R Audio I/O	×
+0.0 dB	3.2	-2.1 dB -9.	Audio Inputs:	1 Input 🗸
🖬 🖱 🖬 OST FX B			Audio Outputs:	1 Output 🗸
1 End Reverb L	2 Reverb R	3 The lay R	Input Channels 01. Channel 1	Output Channels
ల	С	С	Mute u	unused channels
				Ok Cancel
		www.bluec		

It is strongly recommended to rename the plug- ins according to the channel they apply to, as shiwn in the above example.

Additional Tips

Lock the Gate

You may want to lock the gate in the amp simulation editor so that it does not change when loading amp simulation presets: once it has been setup properly (or disabled), you may want to keep the settings that work for you regardless of the select amp.

Pan Amp Sim Channels

You can hard- pan amp sim channels left and right and then adjust the stereo width to blend both sounds in the middle using the master spread control.

Switch between Channels A and B

You can use channels A and B like amp channels in the real world, but with different effect pedals if you want. Assign the A/ B mix parameter to a MIDI footswitch, and use channel B when taking the lead, reserving channel A for rhythm parts!

Save Presets

It is recommended to save your favorite effect chains, amp simulations and channel configuration as presets: this will save you a lot of time when creating new tones. Axiom was designed to help you reuse your work: don't re- invent the wheel everytime!

Also, you should save your favorite third party plug- ins configurations with the "Save As..." menu item: they will appear in the plug- in menu so that you can load them faster.

Use Destructor for More Amp Sims / Distortion Pedals / Cabs

You can instantiate the built- in Destructor plug- in anywhere in the signal chain to create more advanced routings: you can for example use ony the "preamp" section of the plug- in in the input slots, and enable only the destruction and post filters of both built- in amp sims. Just like plugging a preamp into two different power amps and cabinets in the real life!



The post- filter section can also be used alone as separate cabinet simulations.

Additional instances of Destructor will also let you add more distortion pedals to your arsenal: check out the included pedal presets and build your own from there!



Load Cabinets or Reverb Impulse Responses with the built- in EQ

The built- in EQ plug- in can load and manipulate impulse responses (IR), just like the built- in IR loader in Destructor. So if you just want to use an impulse response for a cab simulation anywhere in the signal chain, just load the built- in EQ and drag and drop the IR onto it!



Change the Tone of Your Guitar With the Input Strip

Using the input strip, it is possile to change the tone of your guitar before it reaches the amp channels. So you can use this section to adapt the signal of your guitar before applying other effects. Check out the "Re- Guitaring" presets or the other included input strip presets, such as "Humbuckerizer", "Single Coilizer", "12 String Acoustic" and tweak them to your taste!

Once you like the new tone of your guitar, you can lock the input section and browse the presets!

Multiband Amps and Effects

You can also use the two parallel channels to perform multiband distortion (use different amps and/ or effects for bass and treble): Just insert an EQ as the first pedal in the pre- fx section for both channels. Set up the first one as a lowpass filter (to process only bass) and the other one as a high pass filter (to process only treble). You can then adjust the filters depending on how you want to split the signal. Check the "Dual Band" factory presets to get an idea!

If you want more bands, you can load the <u>PatchWork plug- in</u> inside Axiom, woth the same approach, just more different filters (it has up to 8 parallel chains). Or you can try the <u>MB-7 Mixer plug- in</u>, that provides a complete multiband infrastructure with perfect split and reconstruction of the signal.

Main Features

The standalone application will let you process audio data coming from the inputs of the audio interface and stream it to its output, in real time, without the need for a third party host application. The application also receives MIDI events from all MIDI input interfaces available on the machine, without any particular configuration required.

The core features of the application are the same as the plug- ins versions, except that the application can run on its own.

It is worth noting that user presets are shared between the standalone application and the plug- ins versions, so that presets can be reused between standlone and plug- in sessions.

Application Preferences

General	MIDUL MIDLOA								
General	MIDI In MIDI Out								
	Configuration:	Stereo	(2 in-2	2 out)				~	
	Driver Type:	ASIO						~]
	Audio Device:	ASIO F	Firefac	e US	В		~		
	Sample Rate:	44100	Hz					~]
	Buffer Size:	256					samp	oles	
	Audio Inputs					Audio (Outpu	ıts	
01.	None	~	01.	Ana	log 1	(1)			~
02.	None	~	02.	Ana	log 2	(1)			~
	Tempo:	120.0					b	pm	
	Time Signature:	4			1	4			
		Tap Tem	po Set	tup					-
		Audio Engir	ne le F	lunni	na				
	E	stimated I/O				3			
		Restart A	udio E	ngine	,				

The audio/ MIDI setup for the application is decribed in details in the first launch chapter.

The configuration window above can be displayed using the Edit/ Audio Setup menu item. More information about the various fields can be found in the <u>first launch</u> chapter.

Application Menu

The application menu gives you access to the following commands:

- Edit/ Undo: undo last change.
- Edit/ Redo: redo last undone change.
- · Edit/ Audio Setup: open the preferences window.

Keyboard Shortcuts

To speed up operation, several keyboard shortcuts are available in the standalone application:

On Windows

- CTRL +Z: undo.
- Shift CTRL +Z: redo.
- CTRL +P: open the preferences window.

• ALT +F4: quit the application.

On Mac

- CMD +Z: undo.
- Shift CMD +Z: redo.
- CMD +, or CMD +P: open the preferences window.
- CMD +Q: quit the application.

Troubleshooting

No Sound

if you cannot hear anything coming out of the software, you need to check the audio configuration: open the preferences window (Edit Menu / Audio Setup command), and check that the audio engine is running. If it is not running, you may need to select another audio interface or change the buffer and sample rate settings. If it is running, you may want to select another audio interface or differnt audio inputs and outputs.

Cracks and Pops

If you can hear unwanted "cracks" and "pops" during the performance, you may be experiencing audio dropouts, because the application is using too much CPU. You can try to increase the buffer size in the preferences window to reduce CPU usage, and close other applications that are currently running.

Blue Cat Audio Plug- Ins Basics

This chapter describes the basic features that are common to all our plug- ins. If you are already familiar with our products, you can skip this part.

User Interface Basics

About Skins


Like all Blue Cat Audio plug- ins, Blue Cat's Axiom uses a skinnable user interface. It means that the appearance and behavior of the user interface can be entirely customized.

Especially with third party skins, the experience may be quite different from the one offered by the default skins that we provide. However, our plug- ins and our skinning engine have several standard features that will be available whatever your favorite skin.

More information about custom skins can be found in the skins section.

The Main Toolbar

In most skins, an optional toolbar at the top of the user interface gives you access to the main options and settings of the plug- in:



Smooth Bypass

On the left, the power button can be used to smoothly bypass the plug- in.

Presets Area

At the center of the toolbar, you can see the current preset area (the "Default Settings" box). It displays the name of the current preset, with a "*" at the end if it has been modified since loaded.

The arrows on the left and right let you navigate thru the (factory and user) presets available for the plug- in.

Clicking on the preset name opens the presets menu which lets you manage the presets of the plug- in.

Using the knob on the bottom right of this area, you can reduce the **opacity** of the window, and make it transparent (the actual result may depend on the host application). Additional messages may appear in the area next to this knob, depending on the plug- in.

Some plug- ins may also propose you to **manually select the audio I/ O** inside the plug- in (bottom left of the presets area), regardless of the host configuration. It can be useful for example to save CPU by selecting mono to stereo configurations (instead of full stereo sometimes chosen by default by the host), or add extra channels to manage side chain internally, when the host does not provides any side chain input. Please note that this does not change the number of I/ O seen by the host application.


Commands

The icons in the toolbar give you access the to the following commands that are detailed in the next paragraph:

Icon	Name	Function
	Menu	Open the main menu
\$	Control Settings	Display the controls settings menu (to manage automation and MIDI control, as described <u>here</u>).
5	Undo	Undo
7	Redo	Redo
?	Manual	User Manual
i.	About	About
Q	Zoom	Scale the user interface (from 70% to 200%).

The Main Menu

The main menu is available from the main toolbar, or if you right click anywhere on the background of the plug- in:




- Presets: opens the presets menu to manage presets.
- Preset Skin: opens the skins menu to choose the skin for the current preset and manage alternative skins for the software.
- Undo/ Redo: undo or redo the latest modifications. This includes all changes made to the current preset settings such as MIDI or automation preferences.
- Presets Settings: open the presets settings window. It lets you change the skin, MIDI and automation settings for the current preset.
- Global Settings: open the global settings window. It lets you change the skin, MIDI and automation settings that are used by default in all instances of the plug- in (if not overridden by the current preset).
- User Manual: open this user manual.
- Check for Updates: opens up our website to let you check if any update for this software is available.
- Get More Skins: get more skins for this software.
- Legal Information: browse licensing and misc legal documents.
- About: displays the "about" dialog box.

Controls

Examples

Here are a few examples of typical controls you will encounter in the user interface of our plug- ins:



Interacting with Controls

You can interact with the controls of the plug- in interface either with the mouse or the keyboard.

Setting the keyboard focus on a control (so that it responds to key strokes) may be automatic (when you pass the mouse over it it gets focus) or manual (you have to click on the control to set the focus on it). Note that all host applications behave differently regarding keyboard handling. In some applications you may not be able to use all keys described later in this manual to interact with our plug- ins. It is usually made obvious to you to know the active surfaces of the skin (the places where you can click with the mouse): the mouse cursor usually changes when you can do something on a control. In the default skins delivered with the plug- in, the cursor changes to a small hand or an arrow to tell you when your mouse is over an active control.

Various mouse movements will let you interact with the controls:

Mouse Interaction	Action
Left Click	Acquire focus and start dragging or push (button)
Left Click + Alt Key	Set the value to default
Left Double Click	Acquire focus and launch the "fine tuning" edit box (except button):
Right Click	Set the value to default
Mouse Wheel	Increment or decrement the position (focus required)
Mouse Drag	Change the control position depending on mouse movement (except button)

Keyboard

All control widgets support the following keys (note that some of them are caught by the host and thus never forwarded to the control. For example in Steinberg Cubase SX you cannot use the arrow keys to control the plug- in):

Keys Common to All Controls

Кеу	Action
Up Arrow	Small increment of the position (up or right)
Down Arrow	Small increment of the position (down or left)
Left Arrow	Same as Down Arrow
Right Arrow	Same as Up Arrow
Page Up	Large increment of the position (up or right)
Page Down	Large decrement of the position (down or left)
+	Small increment of the value of the control
-	Small decrement of the value of the control
d	Set to default value (same as mouse right click)
e	Opens the 'fine tuning' window to precisely set the parameter:
SHIFT	When the key is down, the fine tuning mode is on, and you can modify the value with better precision when moving the mouse, the mouse wheel or using the keyboard. Just release the key to get back to the normal mode.

Keys Specific to Buttons

Кеу	Action	
Enter	Pushes the button	
-		

Presets

To get started with the plug- in and discover its capabilities, a couple of factory presets are provided. You can also save your own presets and recall them later for other projects. Our plug- ins propose a full- featured preset manager to let you save, browse, organize and recall its presets.

The Presets Menu

The presets menu can be opened from the <u>main menu</u> or the <u>main toolbar</u>. It displays the list of presets available for the plug- in as well as commands to load, save or organize presets:



- Factory Presets: shows the list of factory presets delivered with the plug- in.
- "Folder A" to "User Preset Z": user presets and categories.
- MIDI Program Change: activate MIDI Program Change support (see below).
- Load: load preset from file.
- Save: save current state to last loaded user preset.
- Save As: save current preset to a file.
- Copy copy preset to the system clipboard.
- Paste paste preset from the system clipboard, if available.
- Save As User Default: save the current state as the default preset. This preset is used every time a new instance of the plug- in is created.
- Clear User Default: reset the default preset to its factory state: this makes the plug- in forgets the custom settings you might have saved as a default preset.

More about Presets

There are two types of presets: factory presets (read only) that are provided with the plug- in, and user presets that can be created and stored by the user.

The user presets are stored in a subdirectory of the documents folders of your profile ("Documents" on Mac, and "My Documents" on Windows): Blue Cat Audio/ [Plug- in Name]/ Presets. Each preset is stored as an individual file. You can create folders and subfolders in the Presets directory to classify your presets, as shown in the example below:

Folder A	۲	User Preset1
Folder B	۲	User Preset2
User Preset X		User Preset3

If you save a preset named "Default" in the root Presets directory, it will override the factory default preset (that's what "Save As Default" does). To restore the factory default preset, you can just remove this file or use the "Reset Default" command.

MIDI Program Change

It is possible to load presets remotely using MIDI "Bank Select" and "Program Change" messages. To enable this feature, select a MIDI channel to receive the events from in the MIDI Program Change menu item from the presets menu:

MIDI Program Change	\checkmark	Disabled
Load		All Channels
Save As		Channel 1
our crism		Channel 2
Сору		Channel 3
Paste		Channel 4
Save As User Default		Channel 5
Clear User Default		Channel 6
		Channel 7
		Channel 8
		Channel 9
		Channel 10
		Channel 11
		Channel 12
		Channel 13
		Channel 14
		Channel 15
		Channel 16

This setting is saved for each plug- in istance with your session but not in presets (except for the default preset, using the "Save as User Default command"). Once activated, the plug- in menu will display the bank number followed by the preset number for each preset:

000 - Factory Presets	۲
001 - Bank01	F
002 - Bank02	F
003/000 - Preset1	
003/001 - Preset2	
003/002 - Preset3	

Every root folder is considered as a new bank, starting with the factory presets (bank 0). Program and bank numbers may change while you add folders and presets, so you should be careful when naming them if bank and program numbers matter to you. It is recommended to use folders to make this task simpler. As a side note, sub folders do not define additional banks (all presets contained in sub folders are associated with the current bank.

As specified by MIDI, bank select messages are not used until a program is actually selected.

MIDI Implementation note: the software supports all types of Bank Select methods. You can use either MIDI CC 0 or MIDI CC 32 to select banks. If both are used simultaneously, they are combined together so that you can use more banks (in this case CC0 is LSB and CC32 is MSB, and actual bank number is 128*CC0+CC32).


MIDI and Automation Control

Blue Cat's Axiom can also be remotely controlled via MIDI using MIDI CC ("Control Change") messages or automation curves, if your host application supports it. It is possible to customize the channel, control numbers, range and response curve used for each parameter in the settings panel available from the <u>main menu</u> (see the <u>Plug- in Settings</u> chapter for more details).

MIDI and Automation Settings Menu

The main menu

Most skins also provide the ability to change MIDI and automation settings directly in the main user interface. Clicking on the control settings icon in the main toolbar opens the following menu:




- Show Control Settings: show direct access to individual control settings for each parameter in the user interface (see next paragraph).
- Lock Control Settings: lock the current controls settings for MIDI and automation so that they remain unchanged when loading presets.
- Use Global Control Settings: ignore the current MIDI/ automation settings and use the global settings instead.
- Control Settings Window: display the control settings window, to change control settings for all parameters.
- Save As Global Control Settings: save the current settings as global settings (used by default, when no specific MIDI/ Automation setting has been set for the cuirrent preset).

Individual Control Settings

When this feature is activated using the "Show Control Settings" item in the MIDI and Automation Settings menu, dropdown menu buttons appears next to the main controls displayed by the plug- in:



Clicking on this button shows the MIDI/ Automation settings menu:



- MIDI Learn: launches MIDI learn mode for the control: touch your MIDI controller and the control will learn from it the MIDI channel and CC number. To end the learn mode, reopen this menu and deselect the option.
- MIDI Unlearn: deactivates MIDI control for this parameter.
- Control Settings: launches the advanced settings panel described below. This controls the settings for the current preset.
- All Control Settings: display the control settings window, with access to all parameters.

Advanced MIDI and Automation Settings

You can completely customize the way the plug- in is controlled by automation and MIDI. For a global view of all parameters at a time, you can use the <u>Plug- in Settings</u> window for the current preset which is available from the main menu.

"Param 5"	- MIDI & /	Automati	ion Setttings	10 A	-	
Enable MIDI	Channel (0-16)	СС (0-127)		Control Response	Control Min	Control Max
	0	5	Leam	Linear 🔹	0 dB	+3 dB

MIDI Settings:

- Enable MIDI: enable/ disable the MIDI control of the parameter.
- Channel: MIDI Channel for the parameter control. If set to 0, the plug- ins will accept Control Change Messages from all MIDI Channels (MIDI Omni mode).
- CC: Control Change Number.
- Learn: click on this button to activate the MIDI learn functionality. When it is activated, you can move your MIDI controller, and the plug- in will automatically set the MIDI Channel and CC Number.

MIDI and automation settings:

- Response: response curve of the MIDI or automation control: from very fast to slow control.
- Min: minimal value of the parameter when MIDI controlled or automated.
- Max: Maximum value of the parameter when MIDI controlled or automated.

Note: if the Min value is higher than the Max value, the response curve will be reversed: increasing the control value will decrease the parameter value.

Note: if you double click on the parameter text control boxes for the max and min values, a "fine tuning" edit box will appear and let you change the min and max values with more precision:

×
dB

More

Check our online tutorial for more screenshots and more examples of our plug- ins user interfaces.

Blue Cat's Axiom Parameters

All parameters described below can be automated and controlled via MIDI if your host application supports it. You can precisely define this behavior in the settings panels described later in this manual.

The parameters of this plug- in exposed for automation and MIDI control are described below:

Name	Unit	Description
General		
Bypass		Bypass the effect.
Meters On		Enable or Disable level meters.
Input Section		
In Gain	dB	Input gain, right at the input of the plug- in, before any processing occurs.
Tuner On		Enable or disable the tuner.
In Bypass 1-4		Bypass input plug- in slots 1 to 4.
Pre Gain	dB	Gain at the end of the input section.
Channel A		
A Enabled		Enable or disable channel A.
A Pre		Enable or disable the Pre effects section of channel A.
A Pre Bypass 1-6		Bypass pre fx plug- in slots 1 to 6 for channel A.
A Amp Bypass		Bypass the amp simulation module for channel A.
A Post		Enable or disable the post effects section of channel A.
A Post Bypass 1-6		Bypass post fx plug- in slots 1 to 6 for channel A.
A Pan	%	Pan pot (left- right panning) for channel A.
A Gain	dB	Output gain for channel A.
Channel B		
Same as Channel A		
A/B		
A- B Mix	%	Relative mix of A and B channels (-100% is A only, 0% is A +B, and 100% is B only).
Master		
Mast Bypass 1-4		Bypass master plug- in slots 1 to 4.
Mast Gain	dB	Master gain at the end of the guitar signal chain, before the brickwall limiter.
Limiter	On/ Off	Enable or disable the 0 dB brickwall limiter.
Tools Slots		
T1-3 Bypass		Bypass tools instrument slots 1 to 3.
T1-3 Gain		Output gain for tools instrument slots 1 to 3.
Out Gain		
Out Gain		Gain at the output of Axiom, after the master signal and tools instruments have

Plug- in Settings

In addition to the controls offered in the main user interface, Blue Cat's Axiom has various settings that let you fine tune the behavior of the plug- in. You can choose to change these settings either for the current preset or globally for all instances of the plug- in.

The Global Settings Window

The settings available in this window *apply to all instances of the plug- in, for all presets*, if not overridden in the <u>presets settings</u>. Consider these settings as "default" settings.

General

You can change the default skin for all instances of the plug- in: write the skin file path in the text edit box or click on the button to open a file chooser dialog. If you have several instances of the plug- in opened in your session, you will have to re- open the user interfaces of these plug- ins to see the skin change.

Blue Cat's Plug-in Global Settings	
General Control Input	
Skin file path:	
C:\Progam Files\Blue Cat Audio\Skins\Default\defaultxml	Browse
Output data refresh rate: 50 Hz	
	Ok Cancel

The output data refresh rate can also be customized for all instances of the plug- in. It controls the refresh rate of non- audio data produced by the plug- in (parameters, curves...). It also controls the refresh rate of output MIDI CC messages or output automation data. The higher the refresh rate, the better precision, but also the higher cpu usage (some host applications may also have trouble recording MIDI data at high refresh rates). The default value is 50 Hz.

Global Control Input Settings (MIDI and Automation)

The plug- in offers a couple of settings that affect the way it is controlled by MIDI messages or automation. While the first settings only apply to MIDI control, the "Control Response", "Min" and "Max" settings apply to *both automation and MIDI control*.

For each parameter you can define a default MIDI channel and CC number. You can then control the plug- in with an external MIDI controller or one of our plug- ins that generate MIDI messages.

The settings below are available for each plug- in parameter.

MIDI Settings:

- Enable MIDI: enable/ disable the MIDI control of the parameter.
- Channel: MIDI Channel for the parameter control. If set to 0, the plug- ins will accept Control Change Messages from all MIDI Channels (MIDI Omni mode).
- CC: Control Change Number.
- Learn: click on this button to activate the MIDI learn functionality. When it is activated, you can move your MIDI controller, and the plug- in will automatically set the MIDI Channel and CC Number.

MIDI and automation settings:


- Response: response curve of the MIDI or automation control: from very fast to slow control.
- Min: minimal value of the parameter when MIDI controlled or automated.
- Max: Maximum value of the parameter when MIDI controlled or automated.

put meters values (0-16) 0 0 0	cc (0-127) 0 1 2	Leam	Control Response Linear ~ Linear ~	Control Min Off	Control Max On	
Channel (0-16) 0 0 0	CC (0-127)		Response Linear ~	Min	Max	
(0-16) 0 0 0	0		Response Linear ~	Min	Max	
0 0 0	1		Linear V		On	
0	1				On	
0		Leam	Linear 🗸			
	2			0 ms	1000 ms	
		Leam	Linear \checkmark	0 ms	500 ms	
0	3	Leam	Linear \lor	0 ms	3000 ms	
0	4	Leam	Linear \checkmark	1 ms	2000 ms	
0	5	Leam	Linear \checkmark	0 dB	+3 dB	
0	6	Leam	Linear \checkmark	0 ms	3000 ms	
0	7	Leam	Linear \vee	0 dB/s	60 dB/s	
0	8	Leam	Linear \vee	0 %	100 %	
0	9	Leam	Linear \vee	Normal	Reversed	
0	10	Leam	Linear \vee	0 %	400 %	
0	11	Leam	Linear \vee	-200 %	+200 %	
0	12	Leam	Linear \vee	0	1	
	0	0 10 0 11	0 10 Leam 0 11 Leam	0 10 Leam Linear V 0 11 Leam Linear V	0 10 Leam Linear ✓ 0 % 0 11 Leam Linear ✓ -200 %	0 10 Leam Linear 0 % 400 % 0 11 Leam Linear -200 % +200 %

(generic screen shot, does not correspond to the actual plug- in parameters)

Note: if the Min value is higher than the Max value, the response curve will be reversed: increasing the control value will decrease the parameter value.

Note: if you double click on the parameter text control boxes for the max and min values, a "fine tuning" edit box will appear and let you change the min and max values with more precision:



"Send MIDI events when parameters values change": activate this option when using a control surface that accepts MIDI events as input. MIDI messages will be sent to the output of the plug- in when the user change the parameters values in the user interface, to keep the software and the controller in sync. MIDI is only sent for parameters that are activated for MIDI control.

The Current Preset Settings Window

In this window you can change the settings for the current preset of the current instance of the plug- in only.

Preset Skin

You can choose to use the global skin setting or to change the skin for the current preset. This way you can have different skins for different instances of the plug- in in the same session in order to differentiate them.

Blue Cat's Plug-in Current Preset Settings	
General Control Input	
✓ Use global skin	
Skin file path:	
C:\Progam Files\Blue Cat Audio\Skins\Default\default.xml Browse	
	Ok Cancel

Preset Control Input Settings (MIDI and Automation)

Use the global settings or override them for the current preset. The parameters are the same as for the global input settings.

Blue Cat's Plug-in Curre	ent Preset S	Settings							x
General Control Input	Control Out	put							
🗹 Use global setting									1
Send MIDI events	when paran	neters values	change						
Parameter Name	Enable MIDI	Channel (0-16)	CC (0-127)		Contro Respon		Control Min	Control Max	
All Parameters		0			Linear	\sim			
Bypass		0	0	Leam	Linear	\sim	Off	On	
Param 1		0	1	Leam	Linear	\sim	0 ms	1000 ms	
Param 2		0	2	Leam	Linear	\sim	0 ms	500 ms	
Param 3		0	3	Leam	Linear	\sim	0 ms	3000 ms	
Param 4		0	4	Leam	Linear	\sim	1 ms	2000 ms	
Param 5		0	5	Leam	Linear	\sim	0 dB	+3 dB	
Param 6		0	6	Leam	Linear	\sim	0 ms	3000 ms	
Param 7		0	7	Leam	Linear	\sim	0 dB/s	60 dB/s	
Param 8		0	8	Leam	Linear	\sim	0 %	100 %	
Param 9		0	9	Leam	Linear	\sim	Normal	Reversed	
Param 10		0	10	Leam	Linear	\sim	0 %	400 %	
Param 11		0	11	Leam	Linear	\sim	-200 %	+200 %	
								Ok	Cancel

(generic screen shot, does not correspond to the actual plug- in parameters)

About Skins

Blue Cat's Axiom integrates Blue Cat's skinning engine that allows you to customize the user interface. You can download alternate skins for your plug- in at the following address:

http://www.bluecataudio.com/Skins/Product Axiom

If you don't find a skin that fits your need or if you want a custom one, you can choose to create your own skin.

Choosing the Skin

There are two ways to select the skin of your plug- in: you can change the default (or 'global') skin, or change the skin for the current preset only (either in the <u>preset settings page</u> or from the main menu). The global skin applies to all plug- in instances (choose this one if you want to use the skin used by default, regardless of the session or preset), whereas the current preset skin only applies to the current preset of the current plug- in instance (use this one if you want to change only the skin for the current session/ preset).

Note: in some host applications, the plug- in window won't resize automatically when you choose a skin with a different size. In this case, just close the window and re- open it: it will be displayed with the right size.

The Skins Menu

The skins menu can be opened from the <u>main menu</u>. It displays the list of skins available for the plug- in as well as commands to manage the skin used by default when no preset skin has been selected:

	Default
	Light
	Custom Skins Other
\checkmark	Use Global Skin Load
	Save As Global Skin

- First Section Factory Skins: shows the list of factory skins delivered with the plug- in ("Default" and "Light" in this example).
- Second Section User Skins: shows the list of user skins that have been installed in the Documents Skins folder for the plug- in (see below).
- Use Global Skin: use the global skin for the current preset/ session (unloads any custom skin previously selected for the current preset).
- Load: opens a file browser dialog to manually select the skin from the file system.
- Save As Global Skin: use the current preset skin as the global skin (loaded by default if no preset skin has been defined).

Installing User Skins

To select user skins directly from the skins menu, install them in the "Skins" directory available in the plug- in's documents folder:

[Your Documents Folder]/ Blue Cat Audio/ [Plugin Name]/ Skins/

The skin engine will scan this folder for new skins (xml files) and display them in the menu. The skin files should be in the root skins folder or in a subdirectory inside this folder: subdirectories are not scanned recursively.

Other Methods to Select Skins

You can also select the skins in the settings panels available from the main menu:

The global skin (used by default if no preset skin has been selected) can be changed in the <u>global settings</u> pane. The current preset skin can be changed in the <u>preset settings page</u>.

Create a Custom Skin

You can create custom skins for your plug- in in order to adapt it to your exact needs. You can change its look and feel and make it completely integrated in your virtual studio!

Just read the <u>Blue Cat's Skinning Language manual</u> and download the samples for the tutorial on <u>http:// www.bluecataudio.com/ Skins</u>. You can get ready to create your own skins in a few minutes. You can then <u>share your skins on our website</u>.

More...

This manual only covers the basics of Blue Cat's Axiom. Our website offers many additional resources for your Blue Cat's Axiom plug- in and is constantly updated, so keep an eye on it! You will find below a few examples of available resources.

Tutorials

Many Tutorials are available on our website. They cover a wide range of topics and host applications.

You can find here a list of tutorials related to the Blue Cat's Axiom plug- in.

Extra Skins

We encourage our customers to propose their own skins for our products and we often propose alternative skins to let you choose the one that best suits your needs. You can check Blue Cat's Axiom <u>skins page</u> to get the latest skins.

Updates

As you can see in the <u>history log</u> below, we care about constantly updating our products in order to give you the latest technology available. Please visit our website often to check if Blue Cat's Axiom has been updated, or subscribe to our <u>Newsletter</u> to be informed of the latest news about our products.

Note: minor version updates are available from the same location as the original full version download (**link received by email upon purchase**). The demo version publicly available on our website will not let you register.

You can also follow us on <u>twitter</u>, <u>facebook</u> and <u>instagram</u> for almost real time updates notification, and subscribe to our <u>YouTube</u> channel to watch the latest videos about our software.

Versions History

V1.62 (2022/03/28)

- Native Apple Silicon (M1) version can now load 64- bit Audio Units that are not compatible with Apple Silicon (via the MacOS bridge).
- New "network slave" mode to run as an audio/ MIDI processing server for the Connector plug- in.
- · Presets can now be loaded via MIDI even when the user interface is closed.
- Improved MIDI events timing precision in the application.
- Windows: ASIO Control panel can now be launched from the audio settings window in the application.
- Audio engine can now be restarted from the audio settings window in the application.
- Fixed MPC Beat plug- in not loading.
- Fixed VST3 version not always loading properly in Ableton Live 11.
- Fixed latency compensation changes not always picked up by host applications.
- VST3: Fixed parameters update issues in Studio One when bouncing tracks.

V1.61 (2021/11/02)

- · Single Installer on Mac (App and all plug- ins formats).
- Fixed issue with amp volume knob and Destructor pedals in EZ mode not using the right parameter in some cases.
- Fixed issues with Wah and Pitch Bender effects when using cheap MIDI controllers not updating values fast enough.
- VST3: fixed random crash in Ableton Live 11 upon load.
- Fixed a crash when loading some VST3 plug- ins that define a bypass parameter beyond the last automatable parameter.
- Fixed an issue with built- in Looper which saved audio loops only as mono.

V1.6 (2021/06/29)

New Features & Improvements:

- Up to 5 times more processing power with the new multicore engine that processes each channel and each tool on a separate core.
- Multicore engine also available for the built- in Late Replies plug- in (Pattern module).
- Improved Tone Maps navigation, with updated user interface (for amp simulation and 9 built- in effects).
- Includes Destructor 1.6 and Late Replies 1.5.
- Updated all 452 factory presets with appropriate drive range for all simulated amps.
- New built- in looper plug- in (in the "Utils" category).
- New built- in distortion and dynamics pedals based on Destructor with new pedal GUI.
- New built- in delay models based on Late Replies 1.5 with new "EZ mode" GUI.
- New DSP workload meter that displays the DSP activity and CPU load.
- Added MIDI control support (MIDI CC messages) for Next and Previous Preset commands, with MIDI learn.
- Improved MIDI & automation control settings with lock, reset and "save as global setting" capabilities.
- Tap Tempo with MIDI CC to set BPM in the application with a footswitch.
- Lock effects bypass switches to match the state of MIDI foot controllers when changing presets.
- Preset files can now be dropped onto the preset LCD area to be loaded.
- Improved buffer management in standalone application on Mac, reducing both latency and CPU usage.
- Level meters, spectrum analyzers and tuner stop processing when the user interface is closed, reducing CPU usage.
- reverted default preset to empty preset to improv performance upon load (the preset is still available as "Default Clean")
- Reduced time to load Axiom or any built- in plug- in.
- Multiple DSP performance improvements.
- Reduced the number of threads used by the plug- in.
- Improved global and preset settings window loading time on Windows.
- Added ability to select the plug- in to load when a shell plug- in file is dragged and dropped onto a slot.
- Full unicode support.

Compatibility:

- Native Apple Silicon (M1 processor) support.
- Dropped 32- bit support on Mac.
- Now requires MacOS 10.9 and newer.

Fixes:

- Fixed standalone app not always asking for Microphone access on most recent MacOS systems.
- Fixed host loop end value not properly passed to hosted plug- ins, for the VST2 version.
- Fixed several crashes upon load for multiple third party plug- ins (mostly VST3).
- Fixed display issues with Waves plug- ins V12 in Mac standalone application.
- Fixed MIDI control for hosted plug- ins not always working when fed with silence.
- Fixed VST3 (and sometimes VST) version freezing Ableton Live upon save on Windows.
- Fixed harmonizer and Pitch Shifter built- in plug- ins that did not always flush their buffer upon bypass (short sounds could be heard when getting out of bypass)

V1.5 (2020/10/05)

New Features & Improvements:

- Tail spillover: activate tail spillover from the toolbar to play effects tail when bypassed (available for Axiom itself or built- in delays and reverbs such as Late Replies). Also applies to sub sections (channel A/ B, Pre or Post FX etc.).
- Revamped Guitar & Bass Factory presets:
 - New hi hain presets using custom impulse responses (IR).
 - New responsive clean and crunch presets.
 - Reduced loudness and spectral balance discrepencies between presets.
 - Adjusted effects levels to preserve loudness when bypassed.
 - Adjusted reverb levels on all presets.
 - Most presets now support input overload gracefully (like "real world" amps): feel free to push the input gain by a few dBs!
 - New default preset to get started quickly with the software.
- Arrow keys can now be used to navigate presets, in the main view or in the presets browser.
- The opacity of the tone map window can now be adjusted for amp simulation and built- in effects.
- · Smoother presets switching.
- Improved smooth plug- in bypass (faster and smoother transition).

Fixes:

- Fixed: built- in Late Replies sometimes cut delay tail when using plug- ins in the feedback loops.
- Fixed: output was mono when both A and B are off and I/ O configuration is mono to stereo.
- Fixed: the state of some VST2 plug- ins (which do not save their state as chunks) were not be restored properly if their number of parameters had been changed (e.g. FabFilter Pro- Q's latest update).
- Mac: fixed GUI performance issues on native P3 displays and improved performance on other displays.
- Mac: fixed mouse wheel that required large movements to change parameter values.
- Mac: fixed mouse cursor flickering issues.
- Mac: fixed Esc key not closing fine edit parameter dialog.
- Mac Audio Unit: fixed plug- in listing in some host applications (Plogue Bidule...).

V1.41 (2020/05/28)

- New high resolution graphics for knobs and sliders.
- Updated Re- Guitar built- in plug- in to version 1.1.
- Reduced disk footprint.
- Fixed several issues with hosted plug- ins bypass (graphical glitches, untriggered bypass...).
- Mac: Fixed keyboard not responding in registration panel in some host applications (LUNA, Garage Band...).
- Mac: Fixed demo version that could hang Logic when reloading projects using the plug- in.

V1.4 (2020/02/03)

- New "stomp box" look & feel for built- in effects.
- New built- in effect: Hot Tuna high performance tuner.
- The tone maps explorer for the amp simulation is now accessible directly from the main user interface.
- Mac application now fully supports dark mode on Mac OS Mojave and newer.

V1.32 (2020/01/06)

New Features & Improvements:

- Navigate presets and create new tones easily with "Tone Maps" for 9 built- in effects: Chorus, Flanger, Phaser, Wah, Sweep Filter, EQ, Freq Shifter, Reverb and Waveshaper.
- New presets for the built- in wah plug- in.
- Built- in EQ & Amp Sim: improved impulse response convolution performance (long reverb tails are now supported, with low CPU usage).
- Mac: faster GUI rendering on recent Mac OS systems (up to 5x faster for level meters).
- Improved built- in tuner performance.

Fixes:

- Mac: fixed user interface not properly shown on retina displays in some applications built with the 10.14 Mac OS SDK (Cubase 10.5 for example).
- Mac: fixed settings panel rendering issues in dark mode on Mac OS Mojave and newer.
- Fixed issue with some VST3 plug- ins that failed to initialize when loaded (Roland Cloud VST3)
- · Fixed built- in Wah plug- in that could exceed selected range in reverse mode.

V1.31 (2019/09/25)

- Fixed tone maps presets morphing that did not work on Mac.
- Fixed tone maps "reload from presets" when the map was created on another platform (Mac vs PC).
- · Fixed persistency of tools rack display setting.

V1.3 (2019/09/23)

New features:

- New <u>amp tones explorer</u> with **amp models morphing**: explore and morph amps in 2 dimensions to create unique new tones easily.
- New presets (and sub- presets) browser with built- in search: find factory or user amp models and effect chains to create new patches.
- Added hundreds of new presets, sub- presets, new amp models (from <u>Destructor 1.5</u>) and new reverbs, delays and modulation effects from <u>Late Replies 1.4</u>.
- MIDI Program Change preference is now saved into session instead of global preferences, so each instance can now use different MIDI channels. It is also saved in the user default preset.
- VST3: added program change support for VST3 plug- in format.
- VST3: added MIDI output support for VST3 plug- in format.

Built- in effects:

- New "Overdrive" and "Overgrind" distortion pedals.
- New Level (volume control) and Micro EQ built- in plug- ins.
- Added a gain parameter to several built- in plug- ins to avoid volume changes when switched on/ off (pitch and frequency shifters, modulation effects, delays).
- Increased knobs precision for pitch shifter and waveshaper built- in plug- ins for smoother control.
- Increased gain control range for distortion pedals.

Third party plug- ins host:

- VST and VST3 plug- ins previously displayed as missing because of name changes are now relocated automatically (Waves major updates, 32 and 64- bit plug- ins with different names etc.)
- Improved auto- relocation performance when a large number of plug- ins have moved.
- VST3 Host: added MIDI output and program change support for recenity updated VST3 plug- ins.

Other fixes and improvements:

- Hovering the mouse on the current preset name now displays a tooltip with the full path of the last loaded preset file.
- Enlarged the area to click on plug- ins bypass and "Show Editor" buttons.
- Improved plug- in and app listing in Windows 10 start menu.
- Fixed an issue with hosted plug- ins editors not always restored in the right position in Cubase on Windows.
- VST: the user interface is now properly resized in Cubase on Windows.
- Mac: fixed issue with Magic Mouse that could trigger drag and drop instead of mouse click.
- Mac: faster GUI rendering on recent Mac OS systems (up to 5x faster on level meters).
- Mac: fixed user interface not properly shown on retina displays in some applications built with the 10.14 Mac OS SDK.
- Spectrum analyzer display of built- in EQ will not take priority over DAW or other plug- ins user interfaces.
- Changing the slope of lowpass and highpass filters in the built- in EQ is now smoother.

V1.2 (2019/03/12)

- New <u>Re- Guitar</u> built- in plug- in.
- New "Re- Guitaring" presets using the new plug- in.
- Fixed issues with Pitch Shifter, Harmonizer and Pitch Bender plug- ins when changing mode (there could be an audible delay).

V1.12 (2018/12/06)

- Spectrum analysis (Amp sim & built- in EQ plug- in) is now performed in the background and does not affect audio performance.
- Audio analysis for the tuner is now performed in the background and does not affect audio performance.
- Improved convolution performance for the impulse response loader on multicore processors.
- Fixed modulation plug- ins that did not always properly set rate when used in host sync mode (sweep filter, flanger, tremolo).

V1.11 (2018/10/19)

- Fixed built- in Late Replies delay plug- in that produced digital distortion when loaded in Axiom presets.
- Fixed built- in multitap delay plug- in that could get out of sync in some host applications.

V1.1 (2018/10/09)

- Load impulse responses (IR) in pre or post filters of the amp simulator. The frequency response of IRs can be shifted and mixed together with the usual filter settings.
- The built- in EQ plug- in can also load and manipulate impulse responses.
- Drag and drop support:
 - drag and drop plug- ins between slots (copy or move).
 drop the plug- in before another to insert it in the chain

 - drag and drop plug- ins between several instances of Axiom or across plug- ins (compatible with the latest preview of Late Replies, MB-7 Mixer and PatchWork).

 - drag and drop .dll, .vst, .vst3, or .component files directly from the Finder or Explorer onto plug- in slots.
 drag and drop .plgnfo files (previously saved from the software) directly from the Finder or Explorer onto plug- in slots.
 - drag the amp simulator, and drop it on any slot, like any other plug- in.
 - drop the amp simulator onto channel A or B to copy the amp model to the other channel.
 - Drag and drop amp channel (A or B) to copy the entire channel settings to the other channel.
- Fixed Joe's Bowl factory preset that included an instance of PatchWork.

V1.0 (2018/04/19)

First release.

Thanks again for choosing our software!

